

Critical Loads and their exceedances; calculation methods and results with focus on EECCA countries

Jean-Paul Hettelingh, Max Posch, Jaap Slootweg
Coordination Centre for Effects (CCE)¹
www.pbl.nl/cce

¹The CCE develops effect-based modelling methodologies and databases for the assessment of environmental effects in Integrated Assessment Models (GAINS) under the Convention on LRTAP with its network of National Focal Centres, and for the European Commission under the LIFE III project EC4MACS (LIFE06 PREP/A/06)



Outline

(focus on critical loads of nutrient nitrogen and heavy metals)

- Critical loads: What, why and how
- Inputs from National Focal Centres (NFCs)
- Challenges in the development and use of critical loads, and the development of NFCs in EECCA countries !

Critical loads: what, why and how

Terminology reminder:

Critical Load (CL, CLo): a deposition (flux) value

Critical Level (CLe): an ambient concentration value

Critical Flux: ... into leaves (for ozone impacts)


General:

Critical Threshold: ... all/any of the above

Damage Function and Critical Load (Threshold):

“In reality” there exist only (experimentally determined) **damage functions**, which often are (or have to be) interpreted probabilistically (“risk of damage”)

Schematic example:



CL: The smooth function is replaced by a step-function (threshold)

Critical load; an early warning for excessive stress (deposition)

Early warning:

- "Critical load" means a quantitative estimate of an exposure to one or more pollutants below which significant harmful effects on specified sensitive elements of the environment do not occur, according to present knowledge;


Is deposition = critical load sufficient for recovery ?:

- Recovery from adverse effects of acidification or eutrophication can be achieved when the critical load is not exceeded. *When recovery is required by a specified year (target year) a deposition value (target load) is required that enables the chemical criterion - that links the critical load to the biological effects - to attain a non-critical value in the target year.*

Note: Target loads are computed using dynamic models !

Methods to derive critical loads

Empirical or modeling approaches



Empirical approach : limited to situations where "pollutant" input dominates effects (e.g. nitrogen i.r.t. biodiversity)

Modeling approach : applicable to all situations in which an environmental quality criterium does exist.

TRANSB04.TC

Source: De Vries ...

Empirical critical loads

- **Europe:** Achermann B and Bobbink (2003), Empirical critical loads for nitrogen, Proceedings of an expert workshop, Berne, 11-13 November 2002.
- **Europe, *next*:** Workshop on the review and revision of empirical critical loads for nutrient N and dose response relationships, organised by the Coordination Centre for Effects in collaboration with the Federal Environmental Agencies from Switzerland and Germany, Noordwijkerhout, 23-25 June 2010, Netherlands

Modeled critical load of nutrient nitrogen and data requirements

$$CL_{nut}(N) = N_{i(crit)} + N_{u(crit)} + N_{l(crit)} + \frac{Q \cdot [N]_{(crit)}}{1 - f_{de}}$$

Nitrogen immobilization.
When assumed "natural"
between 0.2-0.5 kg ha⁻¹
yr⁻¹; Can include

$N_{erosion}$, N_{fire} ,
 $N_{volatilisation}$, $N_{adsorption}$, N_{fix}

Critical nitrogen leaching.
Depends on runoff and
Critical soils solution conc.
The latter vary from 0.2
mg N l⁻¹ (N imbal. Conifers)
to a range of 3-5 mg N l⁻¹
for herbs to become grass

Nitrogen uptake is based on nitrogen
limitation concept, whereby N_u depends
on base cation deposition and
weathering

Denitrification, in Europe
computed w/constant
Denitrification fraction f_{de} ;
0.8 (peat soils), 0.7 (clay soils),
0.5 sandy soils, 0.1 loess soils

Source: CCE Status Report 1993 (www.pbl.nl/cce) and Mapping Manual, www.icpmapping.org

Inputs from National Focal Centres

NFC response for 2008 critical load database

(see CCE Status Report 2008, Ch. 2 & appendix B; www.pbl.nl/cce > publications)

- National Focal Centres (NFCs) are asked to
 - Submit modeled critical loads for acidification and eutrophication (and data to compute them)
 - Submit empirical N critical loads
 - Area of the ecosystem within each EMEP grid cell
 - Protection characteristic (areas subject to e.g. Special Protection, Bird directive, Habitat directive...)
 - Code according to the European Nature Information System (EUNIS: 4 “forest”-, 6 “vegetation”-, 4 “other” classes)
- 20 parties to the Convention, including Canada, responded to the call.

Non-response: Apply CCE background (BG) database

- The European BG-database for modeled critical loads is compiled from, e.g.:
 - Harmonized land cover map (CCE SR 2008) -> *EUNIS; also specifying NATURA 2000 areas*
 - Soil maps from Eurosoil (1999), FAO (1981) -> *transfer function for CEC and B_{sat} , denitrification, N immobilisation*
 - Forest growth map from the European Forest Institute (Schelhaas *et al.*, 1999) -> *nutrient uptake*
 - Database on monthly precipitation, temperature and cloudiness (Mitchell, *et al* 2004) -> *precipitation surplus, soil water content*
 - ...
- These are overlayed to enable the computation of the critical load for acidification and for eutrophication for each EUNIS class, in each EMEP grid cell,
- Map of $Cl_{nut}(N)$ consists of 3 Mkm² NFC-data and 0,7 Mkm² BG-data,
- Map of Empirical critical loads consist of 1.5 Mkm² NFC-data and 0.6 Mkm² BG-data.


Critical (CL) and target loads (TL) of eutrophication:

Target loads are lower than critical loads. Target loads are computed with dynamic models !


Critical loads: When N-deposition is equal to critical loads, this means that ecosystems will recover. However, we do not know when !

Target loads
i.e., recovery by 2050

CLnut(N) (5th percentile) All ecosystems





TLnut(N) (5th percentile) All ecosystems



Exceedance of $CL_{nut}(N)$ for NATURA 2000 areas mapped in 50x50 km² (left) and 5x5 km² (right) grid cells

50 x 50 km grid with N2k areas

5 x 5 km grid with N2k areas





Exceedance of $CL_{nut}(N)$ for NATURA 2000 areas mapped in 50x50 km² (left) and 5x5 km² (right) grid cells

50 x 50 km grid with N2k areas

5 x 5 km grid with N2k areas

A high resolution for critical loads is relevant, only when the resolution of deposition is also high. EMEP plans to increase its resolution from 50x50 km² to 10x10 km² grid cells. Therefore in 2010 the CCE plans to issue a call for data on 10x10 km² !




Preliminary mapping of critical loads and
exceedances of heavy metals
in EECCA countries,
using an extended CCE background database

in collaboration with *EMEP-MSC East*:

Source: Reinds, Ilyin, Groenenberg, Hettelingh
CCE Status Report, 2008

5th percentile critical load of Mercury on forests in EECCA:


This means that 95% of the forests are protected from the effects of mercury deposition, if the deposition is equal to critical loads (see colour ranges)




5th percentile critical load of Cd and Pb on forests in EECCA:

This means that 95% of the forests are protected from the effects of Cd (left map) and Pb deposition (right map), if that deposition is equal to critical loads (see colour ranges)

Cadmium (Cd)



Lead (Pb)





Total annual deposition of Pb on coniferous forests and cropland

Source: EMEP MSC-E


Coniferous forests

Croplands



Average Accumulated Exceedance of lead (Pb):


this is the area weighted average of the difference between lead deposition and critical loads, for all ecosystems in each EMEP grid cell



We need collaboration with
National Focal Centres to
improve the critical loads data at the CCE !

Challenges in the use and development of
critical loads !

Use of critical loads and other effect-based indicators, to support policy !



Source: CCE Status Report 2008

Critical load “Development” benefits

The Effect-based program under the LRTAP Convention in general and the ICP Modelling and Mapping (ICP M&M) in particular:

- Creates a sense of common purpose to improve knowledge on the sensitivity of ecosystems,
- Stimulates steady progress of methodologies and data for the analysis of bio-geochemical as well as biological processes
- Brings together communities that address effects on nature from different perspectives (e.g. ...modellers and field-researchers; “good ecological state” and “air pollution effect” experts ...)
- Offers a common objective to address issues of scale and aggregation
- Enhances the formation of research groups and consortia for making scientific progress, write papers in the open literature and for acquiring funding
- Has provided and still provides broad material for environmental science education and (many) Ph.D research results ranging from natural sciences to systems analysis.

Critical load “Use” benefits

Collaboration between the ICP M&M and policy support community:

- Expedites the broad scale (temporal and spatial) analysis of possible effects of pollution abatement alternatives
- Stimulates an operational trade off between site specific data requirements for effect assessments and broad scale applications of environmental models and (European) integrated assessment
- Strengthens a common knowledge basis for environmental (air quality) policy
- Improves communication between science and (inter-)national policy
- Helps stake holders with assessments (negotiations...) of emission abatement requirements and trade off.
- Enhances the development of region-specific integrated assessment models
- Strengthens multidisciplinary (applied) research
- Substantiates the relevance of research proposals with comprehensive policy applications

Recommendations regarding the development of critical loads methods and data

- Available critical load methods that have been applied in Europe, Asia and Canada. Collaboration with national scientists, via a National Focal Centre (NFC) is vital for improving critical loads in EECCA countries!
- Indicator values and data, especially for critical limits, need to be reviewed and possibly revised for applications tailored to natural areas in the EECCA
- ...However, data collection is not necessarily required for all natural systems; in a first step, focus improvements of critical loads input data on those areas where depositions are likely to exceed critical loads, the latter being established with, e.g. 'fail-safe' (critical limits)
- The CCE is anxious to extend the work of the ICP M&M to include National Focal Centres in EECCA countries!

Please join the effect based work,
under the Convention LRTAP !

Thank you for your attention !

Further information:

- LRTAP Convention, Working Group on Effects (WGE):
www.unece.org/env/lrtap/WorkingGroups/wge/welcome.html
- ICP Modelling and Mapping (manual): www.icpmapping.org
- CCE: www.pbl.nl/cce